

Finding license server automatically or entering additional server name not possible

Technical Support FAQ

Category: Technical Services->Licensing->Wibu Lizenzserver

Programs: Allplan 2021
Allplan 2020
Allplan 2019
Allplan 2018
Allplan 2017
Allplan 2016

Document ID: 20150629140510

Internet: <https://connect.allplan.com/en/faqid/20150629140510.html>

Question:

Why is it not possible to clear the check box for 'Find license server automatically' and why can't I enter an additional server name? These functions are grayed out.

Answer:

This problem is caused by Windows access rights. Only administrators can change these options.

Installing Allplan:

If this problem occurs during Setup and you cannot select a license, start by installing Allplan as a viewer.

Granting permissions later:

Assign full control to the users.

Local permissions prevent them from accessing the following file: Lic3LM.ini

Check whether the users have full control of the following folder:

Click folder with the right mouse button -> Properties -> Security -> Edit -> select the user - > grant full control

C:\ProgramData\Nemetschek(hidden file)

Open the 'License settings' dialog box: **Services application -> Utilities -> License settings** You should now be able to clear the check box and enter additional server names.

Allplan GmbH and affiliated sales organizations not assume any responsibility or liability for the reliability and usefulness of the articles offered and any information provided. You assume sole responsibility for use of the articles offered and the information provided. Terms and conditions of license of Allplan GmbH and / or the general terms and conditions of the sales organizations rendering the service apply.

