

Strange behavior in Allplan

Technical Support FAQ

Category: General Basis Functions->Technic->Operating system

Programs: Allplan 2022
Allplan 2021
Allplan 2020
Allplan 2019
Allplan 2018

Status: 15.12.2021

Document ID: 20200310144447

Internet: <https://connect.allplan.com/en/faqid/20200310144447.html>

Question:

My projects in Allplan are suddenly incomplete, or projects are suddenly missing in the project list. What could be the reason for this?

Response:

Check whether the Windows synchronization is active. Sometimes it can happen that the synchronization was activated by a Windows update.
Then deactivate it again.

To do this, go to the Windows search and enter Control Panel.
Make sure that the Control Panel shows all items. To do this, go to Category at the top right of Display and select 'Small icons' or 'Large icons'.

In Control Panel, go to **Synchronization Center** ->click on left side **Manage Offline Files**.
Here it should say under General - Enable Offline Files.
If Disable Offline Files is displayed here, click on it and use it to disable synchronization.
Then click on Apply.
In order for the settings to be applied, you must now restart your computer.

Now test the behavior in Allplan again.

Allplan GmbH and affiliated sales organizations not assume any responsibility or liability for the reliability and usefulness of the articles offered and any information provided. You assume sole responsibility for use of the articles offered and the information provided. Terms and conditions of license of Allplan GmbH and / or the general terms and conditions of the sales organizations rendering the service apply.

